

Enable Remote Desktop User Access for vSpace 6 on Windows

Microsoft Remote Desktop Services and NComputing vSpace 6 require that users be granted access to Windows remote desktop services. There are at least two ways to enable the access.

- 1. If the vSpace server is part of active directory domain, you can remotely add the desired users to the remote desktop users group inside active directory.
- 2. Even if the server is not part of a domain, you can still enable user access, but you will need to login on EACH vSpace host and grant access locally.

This document explains how to enable user access directly on the local host. If you have more questions about granting domain access, please contact your Domain Administrator.

Go to the Windows Start menu, right click Computer, and select Properties. In the popup window, select Remote Settings.

					- • ×
🔾 🗢 🛃 🕨 Control Panel 🕨	All Control Panel Items 🕨 System	n		✓ Search Control Panel	٩
Control Panel Home Device Manager Remote settings System protection Advanced system settings	View basic information Windows edition Windows 7 Enterprise Copyright © 2009 Microso	about your computer ft Corporation. All rights reserve	d.		
See also Action Center Windows Update Performance Information and Tools	System Manufacturer: Model: Rating: Processor: Installed memory (RAM): System type: Pen and Touch: Milestone Technologies, Inc. s Website:	Technologies, Inc. LENOVO 76641JU 472 Windows Experience Inc Intel(R) Core(TM)2 Duo CPU 3.00 GB 64-bit Operating System No Pen or Touch Input is avail upport Online support	lex T7500 @ 2.20GHz 2. able for this Display	20 GHz	
1003	Computer name, domain, and	workgroup settings		-	

On the "System Properties" popup, replace the default "Don't allow connections to this computer" setting with "Allow connection from computers running any version of Remote Desktop" option. Do NOT select the "Network Level Authentication" option.

System Properties					
Computer Name Hardware Advanced System Protection Remote					
Remote Assistance					
Allow <u>R</u> emote Assistance connections to this computer					
What happens when Lenable Remote Assistance?					
Adyanced					
Remote Desktop					
A You must enable the Windows Firewall exception for Remote Desktop.					
Don't allow connections to this computer					
 Allow connections from computers running any version of Remote Desktop (less secure) 					
Allow connections only from computers running Remote Desktop with <u>N</u> etwork Level Authentication (more secure)					
Help me choose Select Users					
OK Cancel Apply					

After setting the correct Allow Connections radio button, click "Select Users", and click "Add" in the following popup window.

Remote Desktop Users	? 💌			
The users listed below can connect to this computer, and any members of the Administrators group can connect even if they are not listed.				
Add <u>R</u> emove				
To create new user accounts or add users to other groups, go to Control Panel and open <u>User Accounts</u> .				
OK	Cancel			

Now type in the names of individual users or groups you want to have vSpace access to this host. For example you can add individual users by typing in user1, user2, and so on – or you can allow all defined users of this computer by typing in the group name of everyone. After you have entered in the system identifiers of all desired users, click "Check Names", the system will validate your entries, and <u>underline</u> all valid names and/or groups.

Select Users or Groups	? 💌
Select this object type:	
Users or Groups	Object Types
Erom this location:	
NComputing.local	Locations
Enter the object names to select (<u>examples</u>):	
user01	(Check Names
Advanced	OK Cancel

Click Ok to dismiss all of the popup windows, and all the user names and groups entered will be granted access.

If this host is part of a domain, you can type in the group Domain Users to allow access to all users with ID's on the domain. (If you are unsure of what to enter please contact your Domain administrator.)